

CCOnlineLabs INEWB-Security Physical Connections

Frame Relay Switch Configuration

Local Router	Local Interface	Local DLCI	Remote Router	Remote Interface	Remote DLCI
INER1	S0/0/0	102	INER2	S0/0/0	201
INER1	S0/0/0	103	INER3-1	S0/0/0	301
INER1	S0/0/0	110	INER3-2	S0/1/0	311
INER1	S0/0/0	104	INER4	S0/0/0	401
INER1	S0/0/0	105	INER5	S0/0/0	501
INER1	S0/0/0	106	INER6	S0/0/0	601
INER1	S0/0/0	107	INEBB1	S0/0	701
INER2	S0/0/0	201	INER1	S0/0/0	102
INER2	S0/0/0	203	INER3-1	S0/0/0	302
INER2	S0/0/0	213	INER3-2	S0/1/0	312
INER2	S0/0/0	204	INER4	S0/0/0	402
INER2	S0/0/0	205	INER5	S0/0/0	502
INER2	S0/0/0	206	INER6	S0/0/0	602
INER2	S0/0/0	207	INEBB1	S0/0	702
INER3-1	S0/0/0	301	INER1	S0/0/0	103
INER3-1	S0/0/0	302	INER2	S0/0/0	203
INER3-1	S0/0/0	304	INER4	S0/0/0	403
INER3-1	S0/0/0	305	INER5	S0/0/0	503
INER3-1	S0/0/0	306	INER6	S0/0/0	603
INER3-1	S0/0/0	307	INEBB1	S0/0	703
INER3-2	S0/1/0	311	INER1	S0/0/0	113
INER3-2	S0/1/0	312	INER2	S0/0/0	213
INER3-2	S0/1/0	314	INER4	S0/0/0	413
INER3-2	S0/1/0	315	INER5	S0/0/0	513
INER3-2	S0/1/0	316	INER6	S0/0/0	613
INER3-2	S0/1/0	317	INEBB1	S0/0	713

Frame Relay Switch Configuration

Local Router	Local Interface	Local DLCI	Remote Router	Remote Interface	Remote DLCI
INER4	S0/0/0	401	INER1	S0/0/0	104
INER4	S0/0/0	402	INER2	S0/0/0	204
INER4	S0/0/0	403	INER3-1	S0/0/0	304
INER4	S0/0/0	413	INER3-2	S0/1/0	314
INER4	S0/0/0	405	INER5	S0/0/0	504
INER4	S0/0/0	406	INER6	S0/0/0	604
INER4	S0/0/0	407	INEBB1	S0/0	704
INER5	S0/0/0	501	INER1	S0/0/0	105
INER5	S0/0/0	502	INER2	S0/0/0	205
INER5	S0/0/0	503	INER3-1	S0/0/0	305
INER5	S0/0/0	513	INER3-2	S0/1/0	315
INER5	S0/0/0	504	INER4	S0/0/0	405
INER5	S0/0/0	506	INER6	S0/0/0	605
INER5	S0/0/0	507	INEBB1	S0/0	705
INER6	S0/0/0	51	INEBB1	S0/0	51
INER6	S0/0/0	100	INEBB1	S0/0	100
INER6	S0/0/0	101	INEBB1	S0/0	101
INER6	S0/0/0	201	INEBB1	S0/0	201
INER6	S0/0/0	301	INEBB1	S0/0	301
INER6	S0/0/0	401	INEBB1	S0/0	401
INEBB1	S0/0	51	INER6	S0/0/0	51
INEBB1	S0/0	100	INER6	S0/0/0	100
INEBB1	S0/0	101	INER6	S0/0/0	101
INEBB1	S0/0	201	INER6	S0/1/0	201
INEBB1	S0/0	301	INER6	S0/0/0	301
INEBB1	S0/0	401	INER6	S0/0/0	401

Ethernet Connections			
Local Device	Local Interface	Remote Device	Remote Interface
INER1	fa0/0	SW1	fa0/1
INER1	fa1/0	SW2	fa0/1
INER2	fa0/0	SW1	fa0/2
INER2	fa1/0	SW2	fa0/2
INER3	fa0/0	SW1	fa0/3
INER3	fa1/0	SW2	fa0/3
INER4	fa0/0	SW1	fa0/4
INER4	fa1/0	SW2	fa0/4
INER5	fa0/0	SW1	fa0/5
INER5	fa1/0	SW2	fa0/5
INER6	fa0/0	SW1	fa0/6
INER6	fa1/0	SW2	fa0/6
INEBB2	E1/0	SW2	fa0/24
INEBB3	E0/0	SW1	fa0/24

Ethernet Connections			
Local Device	Local Interface	Remote Device	Remote Interface
ACS Server		SW1	fa0/20
Workstation #1		SW2	fa0/20
IPS (C&C)	fa0/0	SW1	fa0/10
IPS (Sensing)	fa0/1	SW2	fa0/10
ASA01	Ma0/0	SW1	Fa0/12
ASA01	Fa0/0	SW2	Fa0/12
ASA01	Fa0/1	SW1	Fa0/13
ASA01	Fa0/2	SW2	Fa0/13
ASA02	Ma0/0	SW1	Fa0/14
ASA02	Fa0/0	SW2	Fa0/14
ASA02	Fa0/1	SW1	Fa0/15
ASA02	Fa0/2	SW2	Fa0/15

Switch to Switch Connections			
Local Device	Local Interface	Remote Device	Remote Interface
SW1	fa0/21	SW2	fa0/21
SW1	fa0/22	SW2	fa0/22
SW1	fa0/23	SW2	fa0/23